

# A2090-619<sup>Q&As</sup>

Assessment: Informix Server 12.10 Assessment

**Pass IBM A2090-619 Exam with 100% Guarantee**

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.pass2lead.com/a2090-619.html>

100% Passing Guarantee  
100% Money Back Assurance

Following Questions and Answers are all new published by IBM Official Exam Center

-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers



**QUESTION 1**

Which type of device does Primary Storage Manager support?

- A. File
- B. Tape
- C. Directory
- D. Named pipe

Correct Answer: A

---

**QUESTION 2**

Which statement is true about restartable restore?

- A. ontape can perform restartable restores if a backup is taken to disk.
- B. Restartable restore is the ability to restart a failed restore using onbar.
- C. Restartable restore is the ability to restart a failed restore using ontape.
- D. Restartable restore is the ability to restart an instance using a restore from some other computer.

Correct Answer: B

---

**QUESTION 3**

The DBA has defined the following configuration parameters in the onconfig file:

```
LOW_MEMORY_MGR 1  
SHMTOTAL 1000000
```

The following SQL command is executed in the SYSADMIN database:

```
EXECUTE FUNCTION task("scheduler lmm enable",  
"LMM START THRESHOLD", "2",  
"LMM STOP THRESHOLD", "3",  
"LMM IDLE TIME", "300");
```

What are the actual values for LMM START THRESHOLD and LMM STOP THRESHOLD computed internally by the database server?

- A. LMM START THRESHOLD = 2MB and LMM STOP THRESHOLD = 3MB
- B. LMM START THRESHOLD = 20MB and LMM STOP THRESHOLD = 30MB

C. LMM START THRESHOLD = 500MB and LMM STOP THRESHOLD = 333MB

D. LMM START THRESHOLD = 2% and LMM STOP THRESHOLD = 3% of physical memory in the system

Correct Answer: B

---

#### QUESTION 4

Which one keyword in this query makes the AVG an OLAP window expression instead of the regular aggregate operator? SELECT AVG(SUM(dollars)) OVER() FROM sales;

A. SUM

B. OVER

C. FROM

D. AVG (SUM(dollars))

Correct Answer: B

---

#### QUESTION 5

The sector option for cdr utility is used to perform what operation?

A. Dynamically convert ER cluster instances in order to perform rolling upgrades.

B. Dynamically convert H/A cluster instances in order to perform rolling upgrades.

C. Dynamically reconfigure Connection Manager SLAs for ER clusters in order to perform rolling upgrades.

D. Dynamically reconfigure Connection Manager SLAs for H/A clusters in order to perform rolling upgrades.

Correct Answer: B

[Latest A2090-619 Dumps](#)

[A2090-619 PDF Dumps](#)

[A2090-619 Practice Test](#)