

DES-1121 Q&As

Specialist - Implementation Engineer PowerMax and VMAX Family Solutions Version 1.0

Pass EMC DES-1121 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

https://www.pass2lead.com/des-1121.html

100% Passing Guarantee 100% Money Back Assurance

Following Questions and Answers are all new published by EMC
Official Exam Center

- Instant Download After Purchase
- 100% Money Back Guarantee
- 365 Days Free Update
- 800,000+ Satisfied Customers



2023 Latest pass2lead DES-1121 PDF and VCE dumps Download

QUESTION 1

What is the largest TDEV PowerMaxOS 5978 can create?

- A. 16 TB
- B. 32 TB
- C. 64 TB
- D. 128 TB

Correct Answer: C

QUESTION 2

A systems administrator no longer needs the remote replica of a local device. Which step can be performed first in order to perform the deletepair function?

- A. Suspend the SRDF link
- B. Split the SRDF link
- C. Change the type of the group to "regular
- D. Change the pair state to "NR"

Correct Answer: A

QUESTION 3

A systems administrator has decommissioned a host with two devices allocated to it. What must the administrator do prior to deleting the devices?

- A. Remove the device attribute
- B. Unmap from the front-end ports
- C. Remove the Storage Group
- D. Delete the Initiators

Correct Answer: C

QUESTION 4

What is the minimum required memory and minimum required disk space to manage a maximum volume count of 64000 and 10 arrays when installing Unisphere for PowerMax?



2023 Latest pass2lead DES-1121 PDF and VCE dumps Download

- A. 8 GB of available memory and 100 GB of available disk
- B. 12 GB of available memory and 120 GB of available disk
- C. 16 GB of available memory and 160 GB of available disk
- D. 24 GB of available memory and 180 GB of available disk

Correct Answer: B

QUESTION 5

An array has reached its capacity m the Storage Resource Pool (SRP). What is the function of the SRP Reserved Capacity?

- A. Accommodate new host writes
- B. Accommodate SRDF/A delta sets
- C. Provide space for snapshot deltas
- D. Provide space for snapshot copies

Correct Answer: B

QUESTION 6

Which PowerMax software packages include NorvDisruplive Migration?

- A. FX and Pro
- B. Essentials and Pro
- C. F and FX
- D. F and Essentials

Correct Answer: A

QUESTION 7

Which SYMCLI command can be used to create a new TDEV and assign it to a Storage Group in one step?

- A. symdev
- B. symsg
- C. symcfg
- D. symaccess



https://www.pass2lead.com/des-1121.html 2023 Latest pass2lead DES-1121 PDF and VCE dumps Download

Correct Answer: D		
QUESTION 8		
Which Solutions Enabler daemon is responsible for Oatekeeper management?		
A. storapid		
B. storsrvd		
C. storslpd		
D. storgnsd		
Correct Answer: C		
QUESTION 9		
A systems administrator wants to know how to convert SRDF ports back to FA ports on their PowerMax array What information should be provided\\'?		
A. A Simplified SymmWin script must be run from the PowerMax MMCS		
B. Change can only be completed using Solutions Enabler or an upgraded bin file		
C. Make the change using Solutions Enabler or Unisphere for PowerMax		
D. Array will require an upgraded bin file to complete the change		
Correct Answer: C		
QUESTION 10		
A systems administrator plans to use Non-Disruptive Migration (NDM) to migrate data from a VMAX array running Enginuity 5876 to a PowerMax running PowerMaxOS 5978 Which NDM mode will be used?		
A. Metro-based		
B. Adaptive Copy		
C. Asynchronous		
D. Pass-through		
Correct Answer: A		
https://www.delltechnologies.com/asset/en-us/products/storage/technical- support/h17133-non-disruptive-migration-best-practices-and-operational-guide.pdf		

2023 Latest pass2lead DES-1121 PDF and VCE dumps Download

QUESTION 11

How does Unisphere 360 differ from Unisphere for PowerMax?

A. Unisphere for PowerMax is the management console for PowerMax and VMAX Family arrays Unisphere 360 provides centralized monitoring for DMX, VMAX Family, and PowerMax arrays

- B. Unisphere for PowerMax provides both GUI and SYMCLI access to PowerMax and VMAX arrays Unisphere 360 provides only GUI access to PowerMax and VMAX arrays.
- C. Unisphere for PowerMax provides centralized monitoring for DMX, VMAX Family, and PowerMax arrays Unisphere 360 is the management console for PowerMax and VMAX Family arrays
- D. Unisphere for PowerMax provides only GUI access to PowerMax and VMAX arrays. Unisphere 360 provides both GUI and SYMCLI access to PowerMax and VMAX arrays.


Correct Answer: C

QUESTION 12


DRAG DROP

On a PowerMax what is the correct sequence of steps to deduplicate data?

Select and Place:



Correct Answer:



QUESTION 13

2023 Latest pass2lead DES-1121 PDF and VCE dumps Download

What will prevent a LUN from being assigned to a second Storage Group?

- A. Both Storage Groups have a service level assigned
- B. A LUN can only be assigned to one Storage Group
- C. Storage Groups are already participating in a Masking View
- D. One of the Storage Groups is a child group

Correct Answer: B

QUESTION 14

An administrator is using Unisphere tor PowerMax Workload Planner to assess the performance and compliance of a PowerMax Storage Group (SG) How does the Planner calculate if the Storage Group workload is stable?

- A. Both calculated values are within a 10-15% threshold of the SL-defined response time
- B. Both calculated values are within the SL-defined response time
- C. One of the calculated values remains within the SL-defined response time
- D. One of the calculated values is within 10-20% of the SL-defined response time


Correct Answer: D

QUESTION 15

DRAG DROP

An SRDF/Metro pair was created with vWitness After a network outage, the administrator discovers that the SRDF pair is in an ActiveBias state What is the correct sequence of events to bring the SRDF pair into an ActiveActive state?

Select and Place:



Correct Answer:



https://www.pass2lead.com/des-1121.html 2023 Latest pass2lead DES-1121 PDF and VCE dumps Download

Establish the SRDF/Metro and select the "Witness" option
Suspend the SRDF/Metro pair
Ensure vWitness is in an Alive state for both the source and target systems
Verify that the Bias is set to the correct site.

DES-1121 PDF Dumps DES-1121 VCE Dumps DES-1121 Practice Test